

Release Notes: MX280005A_V2023.1.1_RevisionHistory.pdf

Previous Release: MX280005A_V2022.6.1.msi

Current Release: MX280005A_V2023.1.1.msi

Beta: NA

Version V2023.1.1 – January 24, 2023

Features

- Added support for MS2720T WCAP files in Analysis/Demodulation (option 0024/0025)
 - Added Auto-capture feature previously released in IQ Acquisition tool. (MX280006A)
 - Added Synchronized Playback for up to 4 files.
 - Added better support for very large IQ data sets.
 - Added 5G Frame Analysis measurement mode.
-

Version V2022.6.1 - June 16, 2022

Features

- Added new User interface combining IQ functionality into a single application
 - Added File Browse mode for locating Anritsu IQ data files
 - Updated file capture by including and updating MX280006A functionality
 - Added Basic IQ viewer mode to view raw IQ data
 - Added IQ file conversion mode
 - Added IQ file playback mode
 - Added IQ Sequencing to Analysis mode
-

Version V2021.3.1 - March 25, 2021

Features

- Support for MS2710xA family of remote spectrum monitors.
- Full support for frame-formatted demodulation.

Bug Fixes

- Fixed issue where the filter roll-off setting was ignored.
- Fixed a memory leak issue caused when demodulation failed completely.
- Fixed several issues with certain modulation types, producing more consistent output.
- Fixed a couple of issues causing unhandled exception errors when loading and displaying